

BULUBOT FW GUIDE v.1.0

8.9.2019

Samet Baykul

FineTuning.cpp

v.1.0.0 : 07.09.2019:

DEFINITION

- Fundamental parameters can be set here

PROPERTIES

SWARM_WIDTH <i>Static</i>	<i>int</i>	Determines how many robots there are in the swarm
UPDATE_DELAY <i>Static</i>	<i>int</i>	Determines the time interval between each calculation step in milliseconds
DIAGNOSIS <i>Static</i>	<i>bool</i>	Turns diagnostic mode on or off. Trace commands do not work when this mode is off
TRACER <i>Static</i>	<i>string</i>	Expresses the definition of the robot that authorizes printing to the console
TOTAL_MOTOR <i>Static</i>	<i>int</i>	Determines how many motors are in a Bulubot
TOTAL_DS <i>Static</i>	<i>int</i>	Determines how many distance sensors are in a Bulubot
TOTAL_LS <i>Static</i>	<i>int</i>	Determines how many light sensors are in a Bulubot
TOTAL_LED <i>Static</i>	<i>int</i>	Determines how many LEDs are in a Bulubot
MOTOR_RPM <i>Static</i>	<i>int</i>	Determines motor speed in rpm
TOTAL_MOTION_TYPES <i>Static</i>	<i>int</i>	Determines how many motion styles can be in a Bulubot at most
TOTAL_MOTION_FRAME <i>Static</i>	<i>int</i>	Determines how many frames can be in each motion style at most

Motion.cpp

v.1.0.0 : 07.09.2019:

DEFINITION

- This **class** allows for *creating* and *optimizing* different motions with legs
- Each **motion** consists of multiple **frames**.
- Each **frame** determines which motor is running or not.
- Each **frame** has equal **time intervals**. These time intervals are determined in **steps**.

METHODS

NEW_MOTION ()

Creates a new motion

Parameters	Types	Description
Motion_Index	<i>int</i>	The index number which is associated with this motion style
Total_Frame	<i>int</i>	The total number of frames which the motion has
Frame_Interval	<i>int</i>	Determines the equal time interval which each frame has in steps
Speed	<i>double</i>	Determines the speed of motors in radians per second

NEW_FRAME()

Creates a new frame

Parameters	Types	Description
Motor_FL	<i>bool</i>	Determines whether the front-left motor is running or not
Motor_FR	<i>bool</i>	Determines whether the front-right motor is running or not
Motor_BL	<i>bool</i>	Determines whether the back-left motor is running or not
Motor_BR	<i>bool</i>	Determines whether the back-right motor is running or not

Output	Types	Description
New_Frame	<i>FRAME</i>	This frame is used as a parameter in the "SET_MOTION_FRAME" method

SET_MOTION_FRAME ()	<p>This method is used to set a frame inside a motion</p> <table><tr><th>Parameters</th><th>Types</th><th>Description</th></tr><tr><td>Motion_Index</td><td><i>int</i></td><td>The index number which is associated with this frame</td></tr><tr><td>Frame_Index</td><td><i>int</i></td><td>The frame index number to be applied on the motion</td></tr><tr><td>Frame</td><td><i>FRAME</i></td><td>Frame object instance to be assigned</td></tr></table>	Parameters	Types	Description	Motion_Index	<i>int</i>	The index number which is associated with this frame	Frame_Index	<i>int</i>	The frame index number to be applied on the motion	Frame	<i>FRAME</i>	Frame object instance to be assigned
Parameters	Types	Description											
Motion_Index	<i>int</i>	The index number which is associated with this frame											
Frame_Index	<i>int</i>	The frame index number to be applied on the motion											
Frame	<i>FRAME</i>	Frame object instance to be assigned											
SET_AFTER_MOTION ()	<p>This method is used to assign the desired function to be triggered when a motion is completed. This method can be used to configure the system control between motions. The continuity of the motion can also be achieved in this way.</p> <table><tr><th>Parameters</th><th>Types</th><th>Description</th></tr><tr><td>Callback Function</td><td><i>Function</i></td><td>The address of the function to be triggered when the motion is completed</td></tr></table>	Parameters	Types	Description	Callback Function	<i>Function</i>	The address of the function to be triggered when the motion is completed						
Parameters	Types	Description											
Callback Function	<i>Function</i>	The address of the function to be triggered when the motion is completed											
START ()	<p>Starts a motion style according to the specified index number</p> <table><tr><th>Parameters</th><th>Types</th><th>Description</th></tr><tr><td>Motion_Index</td><td><i>Function</i></td><td>Index number of the desired motion style</td></tr></table>	Parameters	Types	Description	Motion_Index	<i>Function</i>	Index number of the desired motion style						
Parameters	Types	Description											
Motion_Index	<i>Function</i>	Index number of the desired motion style											
STOP()	<p>Stops all current motions</p>												

Framework.cpp

v.1.0.0 : 07.09.2019:

DEFINITION

- All other properties and methods which are ready to use

PROPERTIES

SPEED <i>Static</i>	<i>double</i>	Speed of the motors [rad/s]
STEP <i>Static</i>	<i>int</i>	Current calculation step
SELF_DEF <i>Static</i>	<i>string</i>	Definition of Bulubot instance

FUNDAMENTAL METHODS

INIT() <i>Static</i>	This function is triggered once at the start
UPDATE() <i>Static</i>	This function is triggered at each step NOTE: In order to set execution frequency: Set "Finetuning -> UPDATE_DELAY"

TRACE METHODS

TRACE()
Static

Print a text

Parameters	Types	Description
Message	<i>string</i>	The message which is wanted to be printed

<div>TRACE_INT()</div> <div>Static</div>	<div>Print an int value with a string label</div> <table><tr><th>Parameters</th><th>Types</th><th>Description</th></tr><tr><td>Label</td><td>string</td><td>The label associated with the value</td></tr><tr><td>Value</td><td>int</td><td>The value which is wanted to be printed</td></tr></table>	Parameters	Types	Description	Label	string	The label associated with the value	Value	int	The value which is wanted to be printed						
Parameters	Types	Description														
Label	string	The label associated with the value														
Value	int	The value which is wanted to be printed														
<div>TRACE_POINT_INT ()</div> <div>Static</div>	<div>Print an int pair values with string labels</div> <table><tr><th>Parameters</th><th>Types</th><th>Description</th></tr><tr><td>Label_1</td><td>string</td><td>The first label associated with the first value</td></tr><tr><td>Label_2</td><td>string</td><td>The second label associated with the second value</td></tr><tr><td>Value_1</td><td>int</td><td>The first value which is wanted to be printed</td></tr><tr><td>Value_2</td><td>int</td><td>The second value which is wanted to be printed</td></tr></table>	Parameters	Types	Description	Label_1	string	The first label associated with the first value	Label_2	string	The second label associated with the second value	Value_1	int	The first value which is wanted to be printed	Value_2	int	The second value which is wanted to be printed
Parameters	Types	Description														
Label_1	string	The first label associated with the first value														
Label_2	string	The second label associated with the second value														
Value_1	int	The first value which is wanted to be printed														
Value_2	int	The second value which is wanted to be printed														
<div>TRACE_DOUBLE ()</div> <div>Static</div>	<div>Print a double value with a string label</div> <table><tr><th>Parameters</th><th>Types</th><th>Description</th></tr><tr><td>Label_1</td><td>string</td><td>The label associated with the value</td></tr><tr><td>Value_1</td><td>double</td><td>The value which is wanted to be printed</td></tr></table>	Parameters	Types	Description	Label_1	string	The label associated with the value	Value_1	double	The value which is wanted to be printed						
Parameters	Types	Description														
Label_1	string	The label associated with the value														
Value_1	double	The value which is wanted to be printed														
<div>TRACE_POINT_DOUBLE ()</div> <div>Static</div>	<div>Print a double pair values with string labels</div> <table><tr><th>Parameters</th><th>Types</th><th>Description</th></tr><tr><td>Label_1</td><td>string</td><td>The first label associated with the first value</td></tr><tr><td>Label_2</td><td>string</td><td>The second label associated with the second value</td></tr><tr><td>Value_1</td><td>double</td><td>The first value which is wanted to be printed</td></tr><tr><td>Value_2</td><td>double</td><td>The second value which is wanted to be printed</td></tr></table>	Parameters	Types	Description	Label_1	string	The first label associated with the first value	Label_2	string	The second label associated with the second value	Value_1	double	The first value which is wanted to be printed	Value_2	double	The second value which is wanted to be printed
Parameters	Types	Description														
Label_1	string	The first label associated with the first value														
Label_2	string	The second label associated with the second value														
Value_1	double	The first value which is wanted to be printed														
Value_2	double	The second value which is wanted to be printed														
<div>TRACE_END()</div> <div>Static</div>	<div>You have to call this function when you are sure to finish the print line. If not, you will GET AN ERROR</div>															
SENSOR METHODS																
<div>READ_SENSOR_DS_L()</div> <div>Static</div>	<div>Returns value of lefts distance sensor</div> <table><tr><th>Output</th><th>Types</th><th>Description</th></tr><tr><td>Value</td><td>double</td><td>Measured current sensor data</td></tr></table>	Output	Types	Description	Value	double	Measured current sensor data									
Output	Types	Description														
Value	double	Measured current sensor data														

READ_SENSOR_DS_R() <i>Static</i>	Returns value of right distance sensor		
	Output	Types	Description
	Value	<i>double</i>	Measured current sensor data
READ_SENSOR_LS () <i>Static</i>	Returns value of light sensor		
	Output	Types	Description
	Value	<i>double</i>	Measured current sensor data
MOTION METHODS			
SET_MOTOR_FL_SPEED () <i>Static</i>	Set speed of the front-left motor		
	Parameters	Types	Description
	Speed	<i>double</i>	Speed in radians per second
SET_MOTOR_FR_SPEED () <i>Static</i>	Set speed of the front-right motor		
	Parameters	Types	Description
	Speed	<i>double</i>	Speed in radians per second
SET_MOTOR_BL_SPEED () <i>Static</i>	Set speed of the back-left motor		
	Parameters	Types	Description
	Speed	<i>double</i>	Speed in radians per second
SET_MOTOR_BR_SPEED () <i>Static</i>	Set speed of the back-right motor		
	Parameters	Types	Description
	Speed	<i>double</i>	Speed in radians per second

SUPERVISOR METHODS

GET_POSITION_X ()

Static

Returns the position of the given robot on the x axis

Parameters	Types	Description
Robot_Index	<i>int</i>	Index number of the target robot in “LIST_ROBOTS” array
Output	Types	Description
Position_X	<i>double</i>	The position of the given robot on the x axis

GET_POSITION_Z ()

Static

Returns the position of the given robot on the z axis

Parameters	Types	Description
Robot_Index	<i>int</i>	Index number of the target robot in “LIST_ROBOTS” array
Output	Types	Description
Position_Z	<i>double</i>	The position of the given robot on the z axis

GET_ROTATION_DEGREE ()

Static

Returns the rotation angle of the given robot in 2D as degree format

Parameters	Types	Description
Robot_Index	<i>int</i>	Index number of the target robot in “LIST_ROBOTS” array
Output	Types	Description
Rotation_Angle	<i>double</i>	The rotation angle of the given robot in degree

GET_ROTATION_RADIAN ()

Static

Returns the rotation angle of the given robot in 2D as radian format

Parameters	Types	Description
Robot_Index	<i>int</i>	Index number of the target robot in “LIST_ROBOTS” array
Output	Types	Description
Rotation_Angle	<i>double</i>	The rotation angle of the given robot in radian

<div>GET_SPEED_X ()</div> <div>Static</div>	<div>Returns the speed of the given robot on the x axis</div> <table><tr><th>Parameters</th><th>Types</th><th>Description</th></tr><tr><td>Robot_Index</td><td>int</td><td>Index number of the target robot in “LIST_ROBOTS” array</td></tr></table> <table><tr><th>Output</th><th>Types</th><th>Description</th></tr><tr><td>Speed_X</td><td>double</td><td>The speed of the given robot on the x axis</td></tr></table>	Parameters	Types	Description	Robot_Index	int	Index number of the target robot in “LIST_ROBOTS” array	Output	Types	Description	Speed_X	double	The speed of the given robot on the x axis
Parameters	Types	Description											
Robot_Index	int	Index number of the target robot in “LIST_ROBOTS” array											
Output	Types	Description											
Speed_X	double	The speed of the given robot on the x axis											
<div>GET_SPEED_Z ()</div> <div>Static</div>	<div>Returns the speed of the given robot on the z axis</div> <table><tr><th>Parameters</th><th>Types</th><th>Description</th></tr><tr><td>Robot_Index</td><td>int</td><td>Index number of the target robot in “LIST_ROBOTS” array</td></tr></table> <table><tr><th>Output</th><th>Types</th><th>Description</th></tr><tr><td>Speed_X</td><td>double</td><td>The speed of the given robot on the z axis</td></tr></table>	Parameters	Types	Description	Robot_Index	int	Index number of the target robot in “LIST_ROBOTS” array	Output	Types	Description	Speed_X	double	The speed of the given robot on the z axis
Parameters	Types	Description											
Robot_Index	int	Index number of the target robot in “LIST_ROBOTS” array											
Output	Types	Description											
Speed_X	double	The speed of the given robot on the z axis											
<div>GET_SPEED ()</div> <div>Static</div>	<div>Returns the speed of the given robot</div> <table><tr><th>Parameters</th><th>Types</th><th>Description</th></tr><tr><td>Robot_Index</td><td>int</td><td>Index number of the target robot in “LIST_ROBOTS” array</td></tr></table> <table><tr><th>Output</th><th>Types</th><th>Description</th></tr><tr><td>Speed</td><td>double</td><td>The speed of the given robot</td></tr></table>	Parameters	Types	Description	Robot_Index	int	Index number of the target robot in “LIST_ROBOTS” array	Output	Types	Description	Speed	double	The speed of the given robot
Parameters	Types	Description											
Robot_Index	int	Index number of the target robot in “LIST_ROBOTS” array											
Output	Types	Description											
Speed	double	The speed of the given robot											

EXAMPLE

```
// -----  
// Bulubot Controller Manin  
// v.1.0.0  
// by Samet Baykul  
// -----  
  
// -----  
// SUPERVISOR  
// -----  
  
// Input all robot definitons in thw swarm here  
  
char LIST_ROBOTS[SWARM_WIDTH][8] = {"BB_1", "BB_2"};  
  
//-----  
// DEFINITIONS  
//-----  
  
// Define your functions here  
  
void Set_Motion();  
void Motion_Update();  
  
//-----  
// MAIN  
//-----  
  
void INIT()  
{  
    // This function is triggered once at the start  
    // Motion Creation  
  
    Set_Motion();  
    MOTION.START(0);  
}  
  
void UPDATE()  
{  
    // This function is triggered at each step  
    // In order to set execution frequency: Set "FineTunning -> UPDATE_DELAY"  
    // These are example of using some important methods which includes some TRACE and SUPERVISOR methods  
  
    TRACE(SELF_DEF);  
    TRACE_POINT_DOUBLE("BB_1 || POS_X", "POS_Z", GET_POSITION_X(0), GET_POSITION_Z(0));  
    TRACE_DOUBLE("ROT", GET_ROTATION_DEGREE(0));  
    TRACE_DOUBLE("SPEED", GET_SPEED(0));  
    TRACE_END();  
    TRACE_POINT_DOUBLE("BB_2 || POS_X", "POS_Z", GET_POSITION_X(1), GET_POSITION_Z(1));  
    TRACE_DOUBLE("ROT", GET_ROTATION_DEGREE(1));  
    TRACE_DOUBLE("SPEED", GET_SPEED(1));  
    TRACE_END();  
}
```

```

}

//-----
// FUNCTIONS
//-----

void Set_Motion()
{
    // Example for creation of a new motion
    // You can edit or define new motion like this

    MOTION.NEW_MOTION(0, 9, 16, SPEED);
    MOTION.SET_MOTION_FRAME(0, 0, MOTION.NEW_FRAME(0, 0, 1, 0));
    MOTION.SET_MOTION_FRAME(0, 1, MOTION.NEW_FRAME(1, 0, 1, 0));
    MOTION.SET_MOTION_FRAME(0, 2, MOTION.NEW_FRAME(1, 0, 1, 0));
    MOTION.SET_MOTION_FRAME(0, 3, MOTION.NEW_FRAME(1, 0, 0, 0));
    MOTION.SET_MOTION_FRAME(0, 4, MOTION.NEW_FRAME(0, 0, 0, 1));
    MOTION.SET_MOTION_FRAME(0, 5, MOTION.NEW_FRAME(0, 1, 0, 1));
    MOTION.SET_MOTION_FRAME(0, 6, MOTION.NEW_FRAME(0, 1, 0, 1));
    MOTION.SET_MOTION_FRAME(0, 7, MOTION.NEW_FRAME(0, 1, 0, 0));
    MOTION.SET_MOTION_FRAME(0, 8, MOTION.NEW_FRAME(1, 1, 1, 1));
    MOTION.SET_AFTER_MOTION(Motion_Update);
}

void Motion_Update()
{
    // This is a call-back function. It is triggered whenever a motion is completed

    MOTION.START(0);
}

```

ERROR CODES			
Error Code	Related Method	Possible Sources	Suggestions
001	Motion.cpp NEW_MOTION() SET_MOTION_FRAME()	Motion_Index Error: The parameter 'Motion_Index' should be less than FineTuning parameter 'TOTAL_MOTION_TYPES'	Increase the parameter, FineTuning.cpp -> TOTAL_MOTION_TYPES
002	Motion.cpp NEW_MOTION() SET_MOTION_FRAME()	Total_Frame Error: The parameter 'Frame_Index' should be less than FineTuning parameter 'TOTAL_MOTION_FRAME'	Increase the parameter, FineTuning.cpp -> TOTAL_MOTION_FRAME